interweb

Generated on 15/11/2026 01:46

KNOWLEDGE BASE · PUBLIC DOCUMENT

How to add swap to a VPS that keeps running out of memory

Administration & Fixes

CODE	VERSION	COUNTRY · LANGUAGE
RLX-MZ-KB-1362	v2026.10.18	Mozambique · English

Interweb Mozambique
RLX Holdings, S.A. · Group RLX Holdings
Tax ID (NUIT) 401 191 607 · Legal entity no. (NUEL) 105 045 974 · Economic activity code (CAE) 62022

https://www.meu.interweb.co.mz/knowledgebase/1362

How to add swap to a VPS that keeps running out of memory

Administration & Fixes Created on **October 10, 2026** Updated on **October 18, 2026** 3 min read



Swap is disk space the system uses as spare memory when the RAM fills up. It does not make the server faster: it exists so that, in a peak, the system **slows down instead of killing processes**. Many new VPS come with no swap at all, which is why the database or the site "vanishes" suddenly: the system ran out of memory and chose the biggest program to shut down (see **out of memory on a VPS: what the OOM killer is**). The commands are yours, on your own server: support does not run them for you (see **how far our support goes**).

First, see whether you have any

Run `free -h` and `swapon --show`. If the "Swap" line of the first shows zero and the second prints nothing, there is no swap. On a KVM server like our VPS, swap is yours to configure.

Creating a swap file

1. **Pick the size.** In the examples below it is 2G, a common starting point on small servers; adjust it to the disk space you can spare. Check the free space first with `df -h`.

2. **Create the file:** `sudo fallocate -l 2G /swapfile`. If that fails, the alternative is `sudo dd if=/dev/zero of=/swapfile bs=1M count=2048` (2048 times 1 MB).

3. **Lock the permissions:** `sudo chmod 600 /swapfile`. Only root should be able to read it, because swap can hold pieces of what was in memory, passwords included.

4. **Prepare and switch it on:** `sudo mkswap /swapfile` and `sudo swapon /swapfile`. Confirm with `swapon --show` and `free -h`.

5 **Make it survive a reboot.** First a copy: `sudo cp /etc/fstab /etc/fstab.bak`. Then add the line `/swapfile none swap sw 0 0` to the end of `/etc/fstab` (for example with `sudo nano /etc/fstab`). A mistake in `fstab` can stop the server booting.

Tuning and undoing

I want to…	Command
See how readily the system uses swap	`cat /proc/sys/vm/swappiness` (the lower, the later it uses it)
Lower the value until the next reboot	`sudo sysctl vm.swappiness=10`
Switch swap off	`sudo swapoff /swapfile`, remove the line from `/etc/fstab` and delete with `sudo rm /swapfile`

Swap is not real memory.
A disk is far slower than RAM: if the server uses swap all the time, the site gets slow with no error showing. Then look at what is eating the memory, and whether the application needs to be lighter or the plan needs more RAM. See **how to see what is using CPU, memory and disk on your VPS**. Each plan's specifications are on the **VPS servers** page.

Measure before and after.
Run `free -h` in a peak before creating the swap, and again after. If the swap's "used" stays near zero, the server was just at its limit; if it climbs and stays high, the cause is elsewhere. Other common problems are in **common VPS and Cloud errors**.

NEED A HAND?

Does the server still run out of memory? Tell us the plan and what runs on it.

Open a support ticket →

SEE ALSO

- **Out of memory on a VPS: what the OOM killer is and what to do** →
- **How to see what is using CPU, memory and disk on your VPS** →

Common VPS and Cloud errors: SSH, memory, disk and reboots →

VPS servers and their plans →

interweb

Interweb Mozambique

RLX Holdings, S.A. · Group RLX Holdings

TAX ID (NUIT)	401 191 607
LEGAL ENTITY NO. (NUEL)	105 045 974
ECONOMIC ACTIVITY CODE (CAE)	62022
REGISTERED OFFICE	Bairro 7 de Setembro Vilankulo 1304 · CEP 0411-02, Inhambane, Mozambique
CONTACT	info@interweb.co.mz · +258 84 635 1111 · +258 86 635 1111 · www.interweb.co.mz
OPENING HOURS	Monday to Friday - 08 AM to 04 PM Saturday & Sunday - Closed

RLX-MZ-KB-1362 · v2026.10.18 · Generated on 15/11/2026 01:46

Online version of this document